#### EXTREME FIRE BEHAVIOR

Virginia's Certified Prescribed

Burning

Managers Program















## Crown Fires

1. What are they?

2. What are the three stages?


### Crown Fire Definition:

A fire involving the crowns of trees or shrubs.

### CROWN FIRE POTENTIAL







# STAGES OF CROWN FIRES

Passive =



Single tree or clumps torching



Active =



Flames in crown supported by surface fire



Independent =



Flames advancing through crowns without surface fire



# CROWN FLAMMABILITY

# Crown Characteristics

- 1. Dead Fuel moisture
- 2. Foliar (live) Fuel moisture

Important: The ratio of dead to live fuel moisture

### Crown Characteristics cont'd

- 3. Foliage Flammability
  Volatile chemicals in fuel
- 4. Crown Closure
  75 % or more
  very helpful in heat transfer



### Surface to Crown Heat Transfer

- 1. Surface fire intensity
- 2. Vertical arrangement (ladder fuels)
- 3. Steepness of slope



### Crown to Crown Heat Transfer

- 1. Crown Spacing
  20 feet or less
  100 stems/acre or more
- 2. Crown level Winds
  20 foot winds of 20 mi/h
  or greater
- 3. Steepness of Slope Acts as wind
























## SPOTTING PROBLEM



## FIREBRAND SOURCE





## TRANSPORTATION





## RECEIVING FUELS AND ENVIRONMENT

Receptive Fuels

Probability of Ignition

Environmental Conditions



## SPOTTING DISTANCES

Long - Range

Short - Range














## Probability of Ignition:

The chance that a firebrand will cause an ignition when it lands on receptive fuels.

## PROBABILITY OF IGNITION



70% or 7 out of 10 firebrands will start a fire.

# Probability of Ignition is calculated for the point of ignition from:

- 1- Hour dead fuel moisture.
- Dry bulb temperature.
- Fuel shading.

#### PROBABILITY OF IGNITION TABLE

	Dry-Bulb Temp. (°F)	FINE DEAD FUEL MOISTURE (PERCENT)															
Shading (Percent)		2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17
	110+	100		80	70	60	60	50	40	40	30	30	20	20	20	20	10
	100-109 90-99	100 100	90 90	80 80	70 70	60 60	60 50	50 40	40 40	40 30	30 30	30 30	20 20	20 20	20 20	10 10	10 10
Unshaded <50% Shaded >50%	80-89	100	90	80	70	60	50	40	40	30	30	20	20	20	10	10	10
	70-79 60-69	100 90	80 80	70 70	60 60	60 50	50 50	40 40	40 30	30 30	30 20	20 20	20 20	20 20	10 10	10 10	10 10
	50-59	90	80	70	60	50	40	40	30	30	20	20	20	10	10	10	10
	40-49 30-39	90 80	80 70	70 60	60 50	50 50	40 40	40 30	30 30	30 20	20 20	20 20	20 10	10	10 10	10 10	10
	110+	100	90	80	70	60	50	50	40	40	30	30	20	20	20	10	10
	100-109 90-99	100 100	90 90	80 80	70 70	60 60	50 50	50 40	40 40	30 30	30 30	30 20	20 20	20 20	20 10	10 10	10 10
	80-89	100		70	60	60	50	40	40	30	30	20	20	20	10	10	10
	70-79 60-69	90 90	80 80	70 70	60 60	50 50	50 40	40 40	30 30	30 30	30 20	20 20	20 20	20 10	10 10	10	10 10
	50-59	90	80	70	60	50	40	40	30	30	20	20	20	10	10	10	10
	40-49 30-39	90 80	80 80	60 60	50 50	50 50	40 40	30 30	30 30	30 20	20 20	20 20	20 10	10 10	10 10	10 10	10 10

### Probability of Ignition Exercises

Example #1

Clear day
No canopy cover
Dry bulb temperature = 86 °F
1- H fuel moisture = 5%

Probability of Igniton = \_\_\_\_\_

## Probability of Ignition Exercises

Example #1

Clear day
No canopy cover
Dry bulb temperature = 86 °F
1- H fuel moisture = 5%


Probability of Igniton = 70%

# PROBABILITY OF IGNITION

Relates only to the chance of initial ignition.

# VORTICES IN WILDLAND FIRE

- Vertical vortices
- Horizontal vortices



## VORTICE DEVELOPMENT


- · Heat source
- · Initiating swirl


## TYPES OF FIREWHIRLS

- Thermally driven
- Convection column vortex
- · Wake type

# THERMALLY DRIVEN

## CONVECTION COLUMN VORTEX





## TWO TYPES OF HORIZONTAL VORTICES

1. Surface - occurs along flanks

2. Column - occurs above the fire

## COMMON DENOMINATORS

- Extreme burning conditions
- Windspeed
- Topography


## CRITICAL CONCERN

Horizontal vortices can occur on the FLANKS of wind-driven and plume-dominated fires.









#### LEAVE YOU WITH

- Need to recognize conditions that are favorable for extreme fire behavior
- Don't burn when these conditions exist
- Be prepared to move from a prescribed burn to a fire suppression mode if necessary
- Crown Fires
- Firewhirls

#### MACK LAKE FIRE

MAY 5, 1980

#### MACK LAKE FIRE

- Which indicators of problem fire behavior were present?
- What other warnings or indicators were present prior to entrapment?
- Summarize the significant lessons you think are to be learned from the Mack Lake Fire.

#### **SHOW VIDEO**

#### DISCUSSION

- Fire Behavior Ladder Fuels, Tight Crown spacing, low RH, high Temperatures, approaching cold front, trees torching, frequent spot fires
- Warnings The weather conditions exceeded the prescription in the Plan, suppression personnel not available, Cold front increase fire danger.

#### LESSONS LEARNED

- Improper tactics given observed fire behavior, need good contingency plan
- Inexperience of tractor plow operator and Engine Crew contributed to the inability to recognize the danger of the situation.
- LCES violated
- Incomplete Briefing
- Exceeding burn presciption limits, lack of attention towards the weather and changing Fire Behavior (spot fires)

## ESCAPE OF PRESRIBED BURN

- Spotting from Slash piles
- Irregular groups of uncut trees adjacent to the prescribed fire area
- Locating the control line near the top of a
   25 percent slope
- High Windspeed (15-plus mi/h)
- Low Relative Humidity (21 percent)
- Low fine fuel moisture (7 percent)